

50 LBS. NET WEIGHT (22.68 KILOS)
COPPER SULFATE CRYSTALS

Classified for
 "RESTRICTED USE"
 in New York State
 under 6NYCRR Part 326

ACTIVE INGREDIENT	BY WEIGHT
COPPER SULFATE PENTAHYDRATE.....	99.0%
OTHER INGREDIENTS.....	1.0%
TOTAL	100.0%

DOC ID 525263

CAS #7758-99-8
 COPPER AS METALLIC NOT LESS THAN 25%

ACCEPTED
 FOR REGISTRATION
 DEC 28, 2010

See back panel for specific pesticidal use directions.

New York State Department
 of Environmental Conservation
 Division of Solid & Hazardous Materials
 Pesticide Product Registration

Also for non-pesticidal uses of copper sulfate including but not limited to:

- For Non-Pesticidal Manufacturing and Industrial Uses.
- For manufacturing, repackaging, formulation of algacides and fungicides.
- For use as foot baths to control hoof rot in cattle.
- For use in preparing Bordeaux mixture.
- For use as a trace mineral for mixing in animal feeds at levels in accord with good feeding and feed manufacturing practices.
- For use as a fertilizer trace mineral for plant growth and used in accord with recommended agronomic practices.

(NOTE: For the states of Wisconsin, California, Oregon and Washington fertilizer recommendations and information, refer to back panel.)

When this product is used as a feed or fertilizer ingredient:
 Guaranteed Analysis: Copper (Cu) = 25.0% Derived from Copper Sulfate

KEEP OUT OF REACH OF CHILDREN
DANGER - PELIGRO

Si usted no entiende la etiqueta, busque a alguien para que se la explique a usted en detalle.
 (If you do not understand the label, find someone to explain it to you in detail.)

FIRST AID	
If on skin or clothing:	Take off contaminated clothing. Rinse skin immediately with plenty of water for 15-20 minutes. Call a poison control center or doctor for treatment advice.
If inhaled:	Move person to fresh air. If person is not breathing, call 911 or an ambulance, then give artificial respiration, preferably by mouth to mouth, if possible. Call a poison control center or doctor for further treatment advice.
If in eyes:	Hold eye open and rinse slowly and gently with water for 15-20 minutes. Remove contact lenses, if present, after the first 5 minutes, then continue to rinse eye. Call a poison control center or doctor for treatment advice.
If swallowed:	Call poison control center or doctor immediately for treatment advice. Have person sip a glass of water if able to swallow. Do not induce vomiting unless told to do so by the poison control center or doctor. Do not give anything by mouth to an unconscious person.
Notes:	Have the product container or label with you when calling a poison control center or doctor, or going for treatment. In the event of a medical emergency, you may also contact the National Pesticide Information Center at 1-800-858-7378.

CHEM ONE LTD. →

This product manufactured for
 CHEM ONE LTD.
 HOUSTON, TEXAS - 77041

EPA REG. NO. 56576-1
 EPA EST. NO. 52117-MX-001

**PRECAUTIONARY STATEMENTS
HAZARDS TO HUMANS AND DOMESTIC ANIMALS
DANGER - PELIGRO**

CORROSIVE: Causes eye damage and irritation to the skin and mucous membranes. Harmful or fatal if swallowed. Do not get in eyes, on skin or on clothing. Do not breathe dust or spray mist. May cause skin sensitization reactions to certain individuals.

PERSONAL PROTECTIVE EQUIPMENT

Applicators and other handlers must wear: Long-sleeved shirt and long pants, chemical-resistant gloves made of any waterproof material, shoes plus socks, and protective eyewear. Some materials that are chemical-resistant to this product are listed below. If you want more options, follow the instructions for category A on an EPA chemical resistance category selection chart. Discard clothing and other absorbent materials that have been drenched or heavily contaminated with this product's concentrate. Do not reuse them. Follow manufacturer's instructions for cleaning/maintaining PPE. If no such instructions for washables, use detergent and hot water. Keep and wash PPE separately from other laundry.

USER SAFETY RECOMMENDATIONS:

Users should: Wash hands before eating, drinking, chewing gum, using tobacco or using the toilet. Remove clothing immediately if pesticide gets inside. Then wash thoroughly and put on clean clothing. Remove PPE immediately after handling this product. Wash the outside of gloves before removing. As soon as possible, wash thoroughly and change into clean clothing.

ENVIRONMENTAL HAZARDS

This product is toxic to fish. Direct application of Copper Sulfate to water may cause a significant reduction in populations of aquatic invertebrates, plants and fish. Do not treat more than one-half of lake or pond at one time in order to avoid depletion of oxygen from decaying vegetation. Allow 1 to 2 weeks between treatments for oxygen levels to recover. Trout and other species of fish may be killed at application rates recommended on this label, especially in soft or acid waters. However, fish toxicity generally decreases when the hardness of water increases. Do not contaminate water by cleaning of equipment or disposal of wastes. Consult your local State Fish and Game Agency before applying this product to public waters. Permits may be required before treating such waters.

STORAGE AND DISPOSAL

PROHIBITIONS: Do not contaminate water, food or feed by storage or disposal. Open burning and dumping is prohibited.
STORAGE: Keep pesticide in original container. Do not put concentrate or dilutions of concentrate in food or drink containers.

PESTICIDE DISPOSAL: Pesticide wastes are acutely hazardous. Improper disposal of excess pesticide, spray mixture, or rinsate is a violation of Federal law. If these wastes cannot be disposed of by use according to label instructions, contact your State Pesticide or Environmental Control Agency, or the Hazardous Waste representative at the nearest EPA Regional Office for guidance.

CONTAINER DISPOSAL: Nonrefillable container. Do not reuse or refill this container. Offer for recycling, if available. Completely empty bag into application equipment. Then dispose of empty bag in a sanitary landfill or by incineration, or if allowed by state and local authorities, by burning. If burned, stay out of smoke.

(FOR RIGID, NONREFILLABLE CONTAINERS)

CONTAINER DISPOSAL: Nonrefillable container. Do not reuse or refill this container. Offer for recycling, if available. Triple rinse as follows: Empty the remaining contents into application equipment or a mix tank. Fill the container ¼ full with water and recap. Shake for 10 seconds. Pour rinsate into application equipment or mix tank or store rinsate for later use or disposal. Drain for 10 seconds after the flow begins to drip. Repeat this procedure two more times.

STORAGE AND DISPOSAL

("residential use")

Do not contaminate water, food or feed by storage or disposal.

STORAGE: Store in original container and place in a locked storage area.

CONTAINER DISPOSAL: Nonrefillable container. Do not reuse or refill this container. **If empty:** Place in trash or offer for recycling, if available. **If partly filled:** Call your local solid waste agency for disposal instructions. Never place unused product down any indoor or outdoor drain..

DIRECTIONS FOR USE

It is a violation of Federal Law to use this product in a manner inconsistent with its labeling.

Do not apply this product in a way that will contact workers or other persons, either directly or through drift. Only protected handlers may be in the area during application. For requirements specific to your State or Tribe, consult the agency responsible for pesticide regulations.

AGRICULTURAL USE REQUIREMENTS

Use this product only in accordance with its labeling and with the Worker Protection Standard, 40 CFR part 170. This standard contains requirements for the protection of agricultural workers on farms, forests, nurseries, and greenhouses, and handlers of agricultural pesticides. It contains requirements for training, decontamination, notification, and emergency assistance. It also contains specific instructions and exceptions pertaining to the statements on this label about personal protective equipment (PPE), and restricted-entry interval. The requirements in this box only apply to uses of this product that are covered by the Worker Protection Standard.

Do not enter or allow worker entry into treated areas during the restricted entry interval (REI) of 24 hours.

PPE required for early entry to treated areas that is permitted under the Worker Protection Standard and that involves contact with anything that has been treated, such as plants, soil, or water, is: Coveralls, chemical-resistant gloves made of any waterproof material (such as polyvinyl chloride, nitrile rubber, or butyl rubber), shoes plus socks, and protective eyewear.

NON-AGRICULTURAL USE REQUIREMENTS

The requirements in this box apply to uses of this product that are NOT within the scope of the Worker Protection Standard for agricultural pesticides (40 CFR Part 170). The WPS applies when this product is used to produce agricultural plants on farms, forests, nurseries, or greenhouses.

Applicators and other handlers who handle this pesticide for any use NOT covered by the Worker Protection Standard (40 CFR Part 170) must wear: long-sleeved shirt, chemical-resistant gloves made of any waterproof material (such as polyvinyl chloride, nitrile rubber, or butyl rubber), shoes plus socks, and protective eyewear.

GENERAL INSTRUCTIONS FOR USE

Water hardness, temperature of the water, the type and amount of vegetation to be controlled, and the amount of water flow are to be considered in using Copper Sulfate to control algae. Begin treatment soon after plant growth has started. If treatment is delayed until a large amount of algae is present, larger quantities of Copper Sulfate will be required. Algal growth is difficult to control with Copper Sulfate when water temperatures are low or when the water conditions are hard water. Larger quantities of Copper Sulfate will be required to kill and control algae in water which is flowing than in a body of stagnant water. If possible, curtail the flow of water before treatment and hold dormant for approximately three days after treatment or until the algae have begun to die. When preparing a Copper Sulfate solution in water, the mixing container should be made of plastic or glass: or, a painted, enameled, or copper lined metal container. It is usually best to treat algae on a sunny day when the heavy mats of filamentous algae are most likely to be floating on the surface where it can be sprayed directly. If there is some doubt about the concentration to apply, it is generally best to start with a lower concentration and to increase this concentration until the algae are killed.

Treatment of algae can result in oxygen loss from decomposition of dead algae. This loss can cause fish suffocation. Therefore, to minimize this hazard, treat one-third to one-half of the water area in a single operation and wait 10 to 14 days in between treatments. Begin treatments along the shore and proceed outward in bands to allow fish to move into untreated water. NOTE: If treated water is to be used as a source of potable water, the metallic copper residual must not exceed 1 ppm (4 ppm copper sulfate pentahydrate).

CALCULATIONS FOR THE AMOUNT OF WATER IMPOUNDED AND FOR THE AMOUNT OF COPPER SULFATE TO BE USED: Calculate water volume as follows: (1) Obtain surface area by measuring of regular shaped ponds or mapping of irregular ponds or by reference to previously recorded engineering data or maps. (2) Calculate average depth by sounding in a regular pattern and taking the mean of these readings or by reference to previously obtained data. (3) Multiply surface area in feet by average depth in feet to obtain cubic feet of water volume. (4) Multiply surface area in acres by average depth in feet to obtain total acre-feet of water volume.

CALCULATE WEIGHT OF WATER TO BE TREATED AS FOLLOWS: (1) Multiply volume in cubic feet by 62.44 to obtain total pounds of water, or (2) Multiply volume in acre feet by 2,720,000 to obtain pounds of water.

CALCULATIONS OF ACTIVE INGREDIENT TO BE ADDED: To calculate the amount of Copper Sulfate Pentahydrate needed to achieve the recommended concentration, multiply the weight of water by the recommended concentration of Copper Sulfate. Since recommended concentrations are normally given in parts per million (ppm), it will first be necessary to convert the value in parts per million to a decimal equivalent. For example, 2 ppm is the same as 0.000002 when used in this calculation. Therefore, to calculate the amount of Copper Sulfate Pentahydrate to treat 1 acre-foot of water with 2 ppm Copper Sulfate, the calculation would be as follows:

$$0.000002 \times 2,720,000 = 5.44 \text{ lbs. Copper Sulfate Pentahydrate}$$

CALCULATION OF WATER FLOW IN DITCHES, STREAMS, AND IRRIGATION SYSTEMS: The amount of water flow in cubic feet per second is found by means of a weir or other measuring device.

SPECIFIC INSTRUCTIONS

SEWER TREATMENT – ROOT DESTROYER*

ROOT CONTROL GENERAL INFORMATION: Plant roots can penetrate through small cracks and poorly sealed joints of sewer lines. If not controlled, these small roots will continue to grow larger in number causing breakage, reduced flow, and eventually, flow stoppage. Copper sulfate has been known to be an effective means to control roots in residential and commercial sewers.

COMMERCIAL, INSTITUTIONAL, AND MUNICIPAL SEWERS:

ROOT CONTROL IN SEWERS: As a preventive measure, apply into each junction or terminal manhole 2 pounds of Copper Sulfate Crystals every 6 to 12 months. At time of reduced flow (some water flow is essential), add copper sulfate. If flow has not completely stopped, but has a reduced flow due to root masses, add Copper Sulfate Crystals in the next manhole above the reduced flow area. For complete stoppage, penetrate the mass with a rod to enable some flow before treatment.

ROOT CONTROL IN STORM DRAINS: Apply when water flow is light. If no water flow, as in dry weather, use a hose to produce a flow. Apply 2 pounds Copper Sulfate Crystals per drain per year. It may be necessary to repeat treatments 3 to 4 times, at 2 week intervals, if drains become nearly plugged.

SEWER PUMPS AND FORCE MAINS: At the storage well inlet, place a cloth bag containing 2 pounds of Copper Sulfate Crystals. Repeat as necessary.

RESIDENTIAL OR HOUSEHOLD SEWER SYSTEMS:

When a reduced water flow is first noticed, and root growth is thought to be the cause, treat with Copper Sulfate Crystals. It is important not to wait until a stoppage occurs because some water flow is necessary to move the Copper Sulfate Crystals to the area of root growth. Usually, within 3 to 4 weeks, after roots have accumulated sufficient copper sulfate, the roots will die and begin to decay and water flow should increase. As the roots regrow, follow-up treatments with copper sulfate will be required. Applications may be made each year in the spring after plant growth begins, during late summer or early fall, or any time a reduced water flow, thought to be caused by root growth, occurs.

Apply 2-6 pounds Copper Sulfate Crystals two times a year to household sewers. Add Copper Sulfate Crystals to sewer line by pouring about ½ pound increments into the toilet bowl nearest the sewer line and flush, repeat this process until recommended dose has been added, or remove cleanout plug and pour entire recommended quantity directly into the sewer line. Replace the plug and flush the toilet several times.

ROOT CONTROL IN SEPTIC TANK AND LEACH LINES AND LEACH LINE PIPES:

SEPTIC TANKS – The majority of the copper sulfate will settle in the septic tank itself and little will pass into the leach lines. To treat leach line pipes, add 2 to 6 pounds of Copper Sulfate Crystals to the distribution box located between the septic tank and the leach lines. To achieve effective root control in the leach lines it is necessary to transfer Copper Sulfate Crystals from the septic tank to the leach lines. A cleanout plug opening may need to be installed if the distribution box does not have an opening leading to the leach lines.

***NOTE:** Do not apply Copper Sulfate Crystals through sink or tub drains as it will corrode the metal drains.

***NOTE:** Copper sulfate added to an active 300 gallon septic tank at 2, 4 and 6 pounds per treatment will temporarily reduce bacterial action, but it will return to normal approximately 15 days after treatment. Trees and shrubbery growing near a treated line normally are not affected due to only a small portion of their roots being in contact with the copper sulfate. The copper sulfate kills only those roots inside the leach line.

***NOTE:** Do not use as a sewer additive where prohibited by State law. State law prohibits the use of this product in sewage systems in the State of Connecticut. Not for sale or use in the California counties of Alameda, Contra Costa, Marin, Napa, San Francisco, San Mateo, Santa Clara, Solano, and Sonoma for root control in sewers. Not for sale or use in septic systems in the State of Florida.

TO CONTROL ALGAE AND THE POTOMOGETON POND WEEDS, LEAFY AND SAGO, IN IRRIGATION SYSTEMS:

Once the amount of Copper Sulfate required for treating ditches or streams has been calculated, use a continuous application method, selecting proper equipment to supply Copper Sulfate granular crystals as follows:

FOR ALGAE CONTROL – Begin continuous addition application of granular Copper Sulfate when water is first turned into the system and continue throughout the irrigation system, applying 0.1 to 0.2 lbs per cubic ft per second per day.

FOR LEAFY AND SAGO POND WEED CONTROL – Use the same continuous feeder, applying 1.6 to 2.4 pounds Copper Sulfate Pentahydrate per cubic foot per second per day. **NOTE:** For best control of leafy and sago pond weed, it is essential to begin Copper Sulfate additions when water is first turned into the system or ditch to be treated and to continue throughout the irrigation system. Copper Sulfate becomes less effective as the alkalinity increases. Its effectiveness is significantly reduced when the bicarbonate alkalinity exceeds 150 ppm. Should Copper Sulfate fail to control pond weeds satisfactorily, it may be necessary to treat the ditch with either a suitable approved herbicide or use a mechanical means to remove excess growth. In either case, resume Copper Sulfate addition as soon as possible.

TO CONTROL ALGAE IN IMPOUNDED WATERS, LAKES, PONDS AND RESERVOIRS: There are several methods by which to apply Copper Sulfate to impounded water. Probably the most satisfactory and simplest method is to dissolve the Copper Sulfate crystals in water and to spray this water over the body of water from a boat. A small pump mounted in the boat can easily be used for this purpose. Fine crystals may be broadcast directly on the water surface from a properly equipped boat. A specially equipped air blower can be used to discharge fine crystals at a specific rate over the surface of the water. When using this method, the direction of the wind is an important factor. Do not use this method unless completely familiar with this type of application. Where the situation permits, Copper Sulfate may be applied under the water by dragging burlap bags containing Copper Sulfate. The crystals are placed in burlap bags and dragged through the water by means of a boat. Begin treatment along the shoreline and proceed outward until one-third to one-half of the total area has been treated. Care should be taken that the course of the boat is such as to cause even distribution of the chemical. In large lakes, it is customary for the boat to travel in parallel lines about 20 to 100 feet apart. Continue dragging the burlap bags over the treated area until the minimum dosage is achieved and all crystals have been dissolved. Large or medium size crystals that dissolve slowly should be used with this method.

Copper Sulfate can be applied to impounded waters by injecting a copper sulfate solution in water via a piping system.

CONTROL OF ALGAE AND BACTERIAL ODOR IN SEWAGE LAGOONS AND PITS (Except California):

Application rates may vary depending on amounts of organic matter in effluent stream or retention ponds. Use 2 lbs. of Copper Sulfate Crystals in 60,000 gals. (8,000 cu. ft.) of effluent to yield 1 ppm of dissolved copper. Dosage levels may vary depending upon organic load. Other Organic Sludges: Copper Sulfate Crystal solution must be thoroughly mixed with sludge. Dissolve 2 lbs. in 1-2 gals. of water and apply to each 30,000 gals. of sludge.

Useful formulas for calculating water volume flow rates: Multiply the water volume in cu. ft. times 7.5 to obtain gallons.

Note: 1 C.F.S./Hr. = 27,000 Gals. 1 Acre Foot = 326,000 Gals.

TO CONTROL ALGAE IN IRRIGATION CONVEYANCE SYSTEMS USING THE SLUG APPLICATION METHOD: Make an addition (dump) of Copper Sulfate into the irrigation ditch or lateral at 0.25 to 2.0 lbs. per cubic foot per second of water per treatment. Repeat on approximate 2-week intervals as required. Depending on water hardness, alkalinity and algae concentration, a dump is usually required every 5 to 30 miles. Effectiveness of Copper Sulfate decreases as the bicarbonate alkalinity increases and is significantly reduced when the alkalinity exceeds approximately 150 ppm as CaCO₃.

TO CONTROL ALGAE IN RICE (Domestic and Wild) FIELDS: Application should be made when algae have formed on the soil surface in the flooded field. Applications are most effective when made prior to the algae's leaving the soil surface and rising to the water surface. Apply 10-15 pounds Copper Sulfate Crystals per acre to the water surface as either crystals or dissolve in water and make a surface spray. Apply higher rate in deeper water (6 inches or greater).

TO CONTROL TADPOLE SHRIMP IN RICE FIELDS: Application should be made to the flooded fields any time the pest appears from planting time until the seedlings are well rooted and have emerged through the water. Apply 5-10 pounds

Copper Sulfate Crystals per acre. The use rate per acre should be determined by the water depth and flow. Use the lower rate at minimum flow and water depth and the higher rate when water depth and flow are maximum.

STATE	SPECIES	BULLETIN NO.	COUNTY
CALIFORNIA	Solano grass	EPA/ES-85-13	Solano
TENNESSEE	Slackwater Darter	EPA/ES-85-04	Lawrence Wayne Hancock
	Freshwater Mussels	EPA/ES-85-07	Claiborne Hawkins Sullivan
ALABAMA	Slackwater Darter	EPA/ES-85-05	Lauderdale Limestone Madison
VIRGINIA	Freshwater Mussels	EPA/ES-85-06	Grayson Smyth Scott Washington Lee

ENDANGERED SPECIES RESTRICTIONS: It is a violation of Federal Law to use any pesticide in a manner that results in the death of an endangered species or adverse modification of their habitat. The use of this product may pose a hazard to certain Federally designated endangered species known to occur in specific areas within the above counties. *****PLEASE NOTE***** Before using this product in the above counties you must obtain the EPA Bulletin specific to your area. This Bulletin identifies areas within these counties where the use of this pesticide is prohibited, unless specified otherwise. The EPA Bulletin is available from either your County Agricultural Extension Agent, the Endangered Species Specialist in your State Wildlife Agency Headquarters, or the appropriate Regional Office of the U.S. Fish and Wildlife Service. **THIS BULLETIN MUST BE REVIEWED PRIOR TO PESTICIDE USE.**

COPPER SULFATE REQUIRED FOR TREATMENT OF DIFFERENT GENERA OF ALGAE

The genera of algae listed below are commonly found in waters of the United States. Use the lower recommended rate in soft waters (less than 50 ppm methyl orange alkalinity) and the higher concentration in hard waters (above 50 ppm alkalinity). Always consult State Fish and Game Agency before applying this product to municipal waters.

ORGANISM	¼ to ½ ppm*	½ to 1 ppm*	1 to 1½ ppm*	1½ to 2 ppm*
Cyanophyceae (Blue-green)	Anabaena Anacystis Aphanizomenon Gloeotrichia Gomphosphaeria Polycystis Rivularia	Cylindrospermum Oscillatoria Plectonema	Nostoc Phormidium	Calothrix Symploca
Chlorophyceae (Green)	Closterium Hydrodictyon Spirogyra Ulothrix	Botryococcus Cladophora Coelastrum Draparnaldia Enteromorpha Gloeocystis Microspora Tribonema Zygnema	Chlorella Crucigenia Desmidium Golenkinia Oocystis Palmella Pithophora Staurastrum Tetraedron	Ankistrodesmus Chara Nitella Scenedesmus
Diatomaceae (Diatoms)	Asterionella Fragilaria Melosira Navicula	Gomphonema Nitzschia Stephanodiscus Synedra Tabellaria	Achnanthes Cymbella Neidium	
Protozoa (Flagellates)	Dinobryon Synura Uroglena Volvox	Ceratium Cryptomonas Euglena Glenodinium Mallomonas	Chlamydomonas Hawmatococcus Peridinium	Eudorina Pandorina

* ¼ - ½ ppm = .67 - 1.3 lbs/acre ft. * 1 - 1½ ppm = 2.6-3.9 lbs/acre ft.
 * ½ - 1 ppm = 1.3 - 2.6 lbs/acre ft. * 1½ - 2 ppm = 3.9 - 5.32 lbs/acre ft.

SCHISTOSOME-INFECTED FRESH WATER SNAILS

For recreational lakes, reservoirs, and ponds, 5.32 -13.3 lbs/acre-ft Copper Sulfate Crystals (i.e., 2-5 ppm copper sulfate), is usually sufficient for treatment of Schistosome-infected fresh water snails. Use surface area in acres multiplied by average depth in feet to determine water volume and application rate. Apply only along shoreline swimming areas and/or

to infected snail beds on a calm sunny day when water temp is at least 60°F. Not allowing swimming for at least 12 hrs following treatment is recommended. If this lower dosage is not sufficient, up to 32 ppm copper sulfate, i.e., 87 lbs/acre (= 2 lbs/1000 sq ft) bottom surface area can be applied. Not allowing swimming for 48 hrs is recommended. Using either dosage, a second application may be made if necessary, 10 to 14 days later. DO NOT make more than two applications a season. Broadcast application using boat, aircraft, or hand equipped with power or hand seeder or underwater dispenser. Do not exceed 1 ppm copper (4 ppm Copper Sulfate) in potable water systems. This labeling must be in the possession of the user at the time of pesticide application. **NOTE : In the State of New York** –For use in recreational lakes, reservoirs and ponds ONLY in areas where infected snail beds have been identified. Apply medium grade crystals by hand broadcast method of application only. This product is a restricted use pesticide in New York State. Pesticide applicator certification or a special use permit is required for sale, possession, or use. Each individual treatment must be approved by the Department of Environmental Conservation. Therefore, you must contact the Pesticide Control Specialist at the appropriate regional office of the Department 30 days in advance of the proposed treatment.

FOOT BATHS FOR CATTLE

Foot baths of Copper Sulfate Crystals can be used as an aid in the treatment of hoof rot in cattle. Prior to treatment, a veterinarian should be consulted to confirm presence of hoof rot. Animals may be walked through a foot bath of 2% (add 2 lbs copper sulfate to 11.8 gals water) to 5% (add 5 lbs copper sulfate to 11.4 gals water) aqueous solution with an immersion time of 5 to 20 min twice daily for a period of time as prescribed by a veterinarian. Keep foot baths clean during treatment period. Do not allow cattle to drink from foot baths as copper sulfate is highly toxic. Follow instructions under Storage and Disposal when solutions are discarded at end of treatment period.

Wisconsin State Copper fertilizer recommendations^a

Washington, Oregon, and California Fertilizer Use

Crop	Pounds per Acre					
	Sands		Loams,silts,clays		Organic	
	Bdct ^b	Band	Bdct ^b	Band	Bdct ^b	Band
Lettuce, onion, Spinach	10	2	12	3	13	4
Carrot, cauliflower, celery, alfalfa, clover, corn, oat, radish, sudan grass, wheat	4	1	8	2	12	3
Asparagus, barley, beans, beet, broccoli, mint, pea, potato, rye, soybean	0	0	0	0	0	2

Information received by the Washington State Dept. of Agriculture regarding the components in this product is available on the internet at <http://agr.wa.gov> Information regarding the contents and levels of metals in this product is available at the Oregon Dept of Agriculture internet site: <http://oda.state.or.us/fertilizer>

^aRecommendations are for inorganic sources of copper. Copper chelates can also be used at 1/6 of the rates recommended above. Do not apply copper unless a deficiency has been verified by plant analysis. ^bBdct = broadcast

BORDEAUX SPRAY MIXTURE

Understanding Bordeaux Formulations: If the Bordeaux mixture instructions read 10-10-100, the first figure indicates the number of lbs of Copper Sulfate Crystals. The second figure is the lbs of hydrated spray lime and the third figure is the gallons of water to be used. Use as a full coverage spray to point of runoff.

Preparation of Bordeaux Spray Mixture: Fill a tank 1/4 full with water. Then, with agitator running, mix in Copper Sulfate Crystals through a copper, bronze, stainless steel or plastic screen. Add water so the tank is 3/4 full. Mix in the hydrated spray lime through the screen and finish filling the tank with water.

CROP USE RECOMMENDATIONS

Almond, Apricot, Peach, Nectarine: Shot Hole Fungus – Prepare a 10-10-100 Bordeaux and apply as a dormant spray in late fall or early spring.

Almond, Apricot, Cherry, Peach, Nectarine, Plum, Prune: Brown Rot Blossom Blight – Prepare a 10-10-100 Bordeaux and apply when buds begin to swell.

Apple: Fireblight – Mix 5 lbs of Copper Sulfate Crystals in 100 gals of water and spray uniformly to the point of runoff. Apply in dormant only at silver tip stage. After silver tip, severe burn will occur on any exposed green tissue. Do not mix lime to make a Bordeaux spray for this treatment.

Blueberries: Bacterial Canker – Prepare and apply an 8-8-100 Bordeaux mixture in the fall before heavy rains begin and again 4 weeks later.

Bulbs (Easter Lily, Tulip, Gladiolus): Botrytis Blight – Prepare a 10-10-100 Bordeaux mixture and apply as a foliar spray to 1 acre. Apply for thorough coverage beginning at the first sign of disease and repeat as needed to control disease at 3 to 10 day intervals. Use the shorter intervals during periods of frequent rains or when severe disease conditions persist. Avoid spray just before flower cutting season if residues are a problem.

Caneberries: For leaf and cane spot and Pseudomonas blight, prepare and apply an 8-8-100 Bordeaux mixture in the fall before heavy rains begin and again 4 weeks later.

Cherry (Sweet): Dead Bud, Bacterial Canker (Pseudomonas Syringae) – Prepare a 12-12-100 Bordeaux. Apply at leaf fall and again in late winter before buds begin to swell. In wet cool Northwest U.S. winters, a third spray may be needed between above sprays.

Cherry (Sour): Leaf Spot – Prepare a 10-10-100 Bordeaux. Apply as a full coverage spray after petal fall or as recommended by the State Extension Service.

CITRUS

(NOTE: Adding foliar nutritionals to spray mixtures containing Copper Sulfate Crystals or other products and applying to citrus during the post-bloom period when young fruit is present may result in spray burn.)

Bacterial Blast – Prepare a 10-10-100 Bordeaux spray and apply a spray in late October to early November or before fall rains begin. Make a complete coverage spray using 10 to 25 gals per mature tree.

Lemon, Orange, Grapefruit: Phytophthora Brown Rot - Prepare a 3-4.5-100 Bordeaux mixture only where there is no history of copper injury or use a 3-2-6-100 (Zinc Sulfate-Copper Sulfate Crystals-Hydrated Lime-Gallons of water) Bordeaux mixture. Spray 6 gals on skirt of tree 3 to 4 ft high and 2 to 4 gals on trunk and ground under tree. If P. hibernalis is present, use 10 to 25 gals to completely cover each tree. Apply in November or December just before or after first rain. In severe brown rot season, apply second application in January or February.

Lemon, Orange, Grapefruit: Septoria Fruit, Leaf Spot; Central California – Brown Rot, Zinc, Copper Deficiencies – Prepare a 3-2-6-100 Bordeaux mixture (Zinc Sulfate-Copper Sulfate Crystals-Hydrated Lime Gallons of water) and use 10 to 25 gals to completely cover each tree. Apply in October, November or December before or just after first rain.

Grape: Downy Mildew – Prepare and apply a 2-6-100 Bordeaux spray beginning when downy mildew is detected. Repeat as needed to achieve and maintain control. This mixture and its use will exhibit some phytotoxicity on most varieties.

Grape (Dormant): Powdery Mildew – Apply in spring before bud-swell and before any green tissue is present. Use 4 to 8 lbs of Copper Sulfate Crystals per 100 gals of water. Apply in a high volume spray of 300 gals water per acre. Direct spray to thoroughly wet the dormant vine, especially the bark of the trunk, head or cordons.

Olive: Olive Leaf Spot (Peacock spot), Olive Knot – Prepare a 10-10-100 Bordeaux and apply up to 500 gals per acre. Apply in autumn before heavy winter rains to prevent peacock spot. In wet winters, a repeat spray may be needed in mid-winter. In areas with less than 10 inches of annual rainfall, a 5-5-100 Bordeaux applied in up to 500 gals per acre may be used. To help protect against olive knot, apply a 10-10-100 Bordeaux before heavy rains and again in the spring. Injury may occur in areas of less than 10 inches of rainfall.

Peach: Leaf Curl – Prepare a 10-10-100 Bordeaux and apply at leaf fall or as a dormant spray in late fall or early spring before buds begin to swell.

Potatoes: To enhance vine-kill and suppress late blight, apply 10 lbs. per acre in 10 to 100 gals of water (ground equipment) or in 5 to 10 gals (aerial equipment) with Diquat at vine-kill to enhance vine desiccation and suppress late blight. Additional applications can be made with Diquat if needed to within 7 days of harvest. Copper Sulfate Crystals may be applied alone until harvest to suppress late blight. NOTE: This product can be mixed with Diquat for use on potatoes in accordance with the most restrictive of label limitations and precautions. No label dosage rates should be exceeded.

Walnuts: Walnut Blight – Apply 15 lbs with 10 lbs of lime in 100 gals of water. Make application in early pre-bloom before catkin blooms are showing (10-20% pistillate) before or after rain. Use only if Bordeaux mixture has been shown to be non-phytotoxic in your area. If desired, add one-half gal summer oil emulsion per 100 gals of water. NOTE: Addition of summer oil emulsion to pre-bloom and early bloom sprays may result in plant injury.

GENERAL CHEMIGATION INSTRUCTIONS

Apply this product only through one or more of the following types of systems: sprinkler including center pivot, lateral move, end tow, side (wheel) roll, traveler, big gun, solid set, or hand move irrigation system(s). Do not apply this product through any other type of irrigation system. Crop injury, lack of effectiveness, or illegal pesticide residues in the crop can result from nonuniform distribution of treated water. If you have questions about calibration, you should contact State Extension Service specialists, equipment manufacturers or other experts. Do not connect an irrigation system (including greenhouse systems) used for pesticide application to a public water system unless the pesticide label-prescribed safety devices for public water systems are in place. A person knowledgeable of the chemigation system and responsible for its operation or under the supervision of the responsible person, shall shut the system down and make necessary adjustments should the need arise.

Posting of areas to be chemigated is required when 1) any part of a treated area is within 300 feet of sensitive areas such as residential area, labor camps, businesses, day care centers, hospitals, in-patient clinics, nursing homes or any public areas such as schools, parks, playgrounds, or other public facilities not including public roads, or 2) when the chemigated area is open to the public such as golf courses or retail greenhouses. Posting must conform to the following requirements. Treated areas shall be posted with signs at all usual points of entry and along likely routes of approach from the listed sensitive areas. When there are no usual points of entry, signs must be posted in the corners of the treated areas and in any other location affording maximum visibility to sensitive areas. The printed side of the sign should face away from the treated area towards the sensitive area. The signs shall be printed in English. Signs must be posted prior to application and must remain posted until foliage has dried and soil surface water has disappeared. Signs may remain in place

indefinitely as long as they are composed of materials to prevent deterioration and maintain legibility for the duration of the posting period. At the top of the sign shall be the words "KEEP OUT", followed by an octagonal stop sign symbol at least 8 inches in diameter containing the word "STOP". Below the symbol shall be the words "PESTICIDES IN IRRIGATION WATER". All words shall consist of letters at least 2 ½ inches tall, and all letters and the symbol shall be a color that sharply contrasts with their immediate background. This sign is in addition to any sign posted to comply with the Worker Protection Standard.

CHEMIGATION SYSTEMS CONNECTED TO PUBLIC WATER SYSTEMS:

Public water system means a system for the provision to the public of piped water for human consumption if such system has at least 15 service connections or regularly serves an average of at least 25 individuals daily at least 60 days out of the year. Chemigation systems connected to public water systems must contain a functional, reduced-pressure zone, backflow preventer (RPZ) or the functional equivalent in the water supply line upstream from the point of pesticide introduction. As an option to the RPZ, the water from the public water system should be discharged into the reservoir tank prior to pesticide introduction. There shall be a complete physical break (air gap) between the flow outlet end of the fill pipe and the top or overflow rim of the reservoir tank of at least twice the inside diameter of the fill pipe. The pesticide injection pipeline must contain a functional, automatic, quick-closing check valve to prevent the flow of fluid back toward the injection pump. The pesticide injection pipeline must contain a functional, normally closed, solenoid-operated valve located on the intake side of the injection pump and connected to the system interlock to prevent fluid from being withdrawn from the supply tank when the irrigation system is either automatically or manually shut down. See Treatment Instructions, below.

SPRINKLER CHEMIGATION:

The system must contain functional interlocking controls to automatically shut off the pesticide injection pump when the water pump motor stops, or in cases where there is no water pump, when the water pressure decreases to the point where pesticide distribution is adversely affected. Systems must use a metering pump, such as a positive displacement injection pump (e.g., diaphragm pump) effectively designed and constructed of materials that are compatible with pesticides and capable of being fitted with a system interlock. The system must contain a functional check valve, vacuum relief valve, and low pressure drain approximately located on the irrigation pipeline to prevent water source contamination from backflow. The pesticide injection pipeline must contain a functional, automatic, quick-closing check valve to prevent the flow of fluid back toward the injection pump. This pipeline must also contain a functional, normally closed, solenoid-operated valve located on the intake side of the injection pump and connected to the system interlock to prevent fluid from being withdrawn from the supply tank when the irrigation system is either automatically or manually shut down. The system must contain functional interlocking controls to automatically shut off the pesticide injection pump when the water pump motor stops. The irrigation line or water pump must include a functional pressure switch which will stop the water pump motor when the water pressure decreases to the point where pesticide distribution is adversely affected. Systems must use a metering pump, such as a positive displacement injection pump (e.g., diaphragm pump) effectively designed and constructed of materials that are compatible with pesticides and capable of being fitted with a system interlock.

TREATMENT INSTRUCTIONS:

Do not apply when wind speed favors drift beyond the area intended for treatment. When mixing, fill nurse tank half full with water. Add Copper Sulfate Crystals slowly to tank while hydraulic or mechanical agitation is operating and continue filling with water. Stickers, spreaders, insecticides, nutrients, etc. should be added last. If compatibility is in question, use the compatibility jar test before mixing a whole tank. Because of the wide variety of possible combinations which can be encountered, observe all cautions and limitations on the label of all products used in mixtures. Copper Sulfate Crystals should be added through a traveling irrigation system continuously or at the last 30 minutes of solid set or hand moved irrigation systems. Agitation is recommended.

NOTICE: CHEM ONE LTD. warrants that this product conforms to the chemical description on the label thereof and is reasonably fit for purposes stated on such label only when used in accordance with directions under normal use conditions. It is impossible to eliminate all risks inherently associated with use of this product. Crop injury, ineffectiveness or other unintended consequences may result because of such factors as weather conditions, presence of other materials, or the manner of use or application, all of which are beyond the control of CHEM ONE LTD. To the extent consistent with applicable law, CHEM ONE LTD. shall not be liable for consequential, special or indirect damages resulting from the use or handling of this product. To the extent consistent with applicable law, all such risks shall be assumed by the Buyer. To the extent consistent with applicable law exclusive remedy of any buyer or user of this product for any and all losses, injuries, or damages resulting from or in any way arising from the use, handling or application of this product, whether in contract, warranty, tort, negligence, strict liability or otherwise, shall not exceed the purchase price paid for this product or at CHEM ONE LTD.'s election, the replacement of this product. CHEM ONE LTD. MAKES NO WARRANTIES OF MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE NOR ANY OTHER EXPRESS OR IMPLIED WARRANTY EXCEPT AS STATED ABOVE.

CHEM ONE LTD.

14140 Westfair East Drive
HOUSTON, TEXAS - 77041
TEL: (713) 896-9966

ENVIRONMENTALLY HAZARDOUS SUBSTANCES
SOLID, N.O.S. (CUPRIC SULFATE) UN3077, RQ

Revisions---

Revised 3-22-06 by notification to restore original language to Specific Instructions---control algae in irrigation conveyance systems
1-31-2006 Bordeaux, storage and disposal, Florida septic systems---changes and additions (Bordeaux) are indicated

Jan 29 2008- remove the 1-800- CLEANUP statement
6-16-08- storage and disposal revise following Pr 2007-4 instructions
6-17-08 Change weight from 22.7 kilos to 22.68 kilos
7-25-08 warranty statement notification
10-29-08- address change for January 2009
06-08-10 add rigid container residue disposal directions