

Minit Installation Guide

Minit Analyst Client

Table of Contents

1. Introduction	3
2. Installation	4
2.1. Prerequisites.....	4
2.2. Communication certificates.....	5
2.3. Installation.....	6
3. Configuration	12
4. Uninstallation	17

1. Introduction

This guide is intended for users of Minit Analyst Edition or Minit Cloud Trial looking for a step-by-step guide to getting Minit Analyst Client installed, set-up and configured on their personal computers.

2. Installation

2.1. Prerequisites

Recommended hardware and standard software configuration for Minit Analyst Client.

CPU	2 cores
RAM	4 GB RAM
HDD	SSD hard drive
Operating System	Windows 10 Desktop – x64 (Recommended)
Other standard software	.NET 4.7.1
Screen resolution	Recommended - 1920x1080 Minimum - 1280x768
Open ports	1719
PowerShell scripts	enabled

To install Minit Analyst Client please, download the installation package and save it to your hard drive. To start the installation, run the downloaded installation package and follow the steps below.

Minit will install under the credentials of the currently logged-in user. Please keep in mind, that only the currently logged-in user will be able to run and use Minit.

To use Minit Analyst Client, a corresponding Minit Analyst Server is required. Please ask your administrator to provide the server address and login credentials.


If you are installing a trial version Client application which will connect to Minit Cloud Trial Server, corresponding connection parameters have been provided with the link to download the installation package. If not, please contact Minit support team at support@minit.io.

2.2. Communication certificates


Minit installs communication certificate automatically. If your security policy doesn't allow for automatic installation of certificates, a manual installation of the new certificate will be required before you can install Minit. If this is your case, please contact Minit support team at support@minit.io. They will provide required communication certificates and tutorial how to install it manually.

2.3. Installation

Run Minit installer and choose the **New Minit installation** option.




Please read and accept the end user license agreement.




You can choose if you want to create a desktop shortcut to Minit Client under the currently logged-in user.

Minit installation location will be chosen automatically.




Before Minit Analyst installation is started, installer checks all software and system requirements. You can see on summary page result of each check.

If one of the steps didn't pass, please click on failed step and follow suggested actions.




You can see installation progress.



Congratulations! You have successfully installed Minit Client. You can choose if Minit Client should be started after installation window is closed.


If any issues occurred during the installation, Minit will automatically create log files. Please save these files and include them when contacting Minit Support at support@minit.io.



3. Configuration

When you run the application for the first time, a configuration wizard will guide you through the application environment setup.

Choose your preferred application language.




Select installation type.

Trial

Choose this option when you want to connect to Minit cloud trial server.

Minit Analyst Edition

Choose this option when you want to connect to existing Minit server used by your company.



Enter Minit server address to which you want to connect. It is also possible to add server connection after configuration wizard is closed. You can find connections under general application settings.

Select **Domain user account** or **Basic account** and enter credentials of the user that will connect to Minit server. This user needs to be created in Minit server first.

The screenshot shows the 'Authentication details' step of the Minit Analyst Server installation wizard. The main content area is white and contains the following elements:


- Section Header:** 'Authentication details'
- Instruction:** 'Please fill Enterprise server name'
- Form Field:** 'Server name:' with a text input box containing a vertical cursor. Below it is the text '(contact your administrator to obtain)'. The input box is highlighted with a red border.
- Form Field:** 'Please select your authentication type' with a dropdown menu showing 'Basic user account' and a downward arrow. The dropdown is highlighted with a red border.
- Form Field:** 'Login name' with a text input box. The input box is highlighted with a red border.
- Form Field:** 'Password' with a text input box. The input box is highlighted with a red border.
- Navigation:** At the bottom left is a grey button with a left arrow and the text 'PREVIOUS STEP'. At the bottom right is a blue button with the text 'NEXT STEP' and a right arrow.

On the right side, there is a vertical sidebar with a pink-to-orange gradient background. It contains the following elements:

- Progress:** 'Skip wizard >>' with a close icon (X) at the top right. Below it are four numbered steps: 1, 2, 3, and 4. Step 2 is circled in white, indicating the current step.
- Icon:** A database icon (cylinder) in the center.
- Text:** 'Authentication' below the icon.
- Logo:** The 'minit' logo at the bottom.


Minit will try to connect to Minit server with provided credentials. It might take a while, please wait for the result.

If connection is not successful, please check Minit address and provided username and password. Make sure that user is created in Minit server with same credentials.




Congratulations! You have successfully configured Minit.

Press **Apply and Mine** to save your configuration settings and start Minit Client.




4. Uninstallation

To uninstall Minit, use the Add or Remove Programs feature in Windows Settings to locate Minit Application and click the uninstall option.




Choose the Remove Minit installation option.




Let the **KEEP SETTINGS** option checked to keep the Minit configuration for further use.

Otherwise, you will need to configure the new installation again.



Minit will inform you about uninstallation progress.



Congratulations! You have successfully uninstalled Minit. If any issues occur during the uninstallation, Minit will automatically create log files. Please save these files and include them when contacting Minit Support at support@minit.io.

